

Mira for Windows


Installation Guide

Quick Start for Windows 32-bit and 64-bit

1. Install the latest Max:
<http://cycling74.com/downloads/>
 2. Install the Apple Bonjour libraries:
<http://support.apple.com/kb/dl999>
 3. Install the Mira package:
http://cycling74.com/direct-download/mira/package_latest_win
-

Detailed Installation for Windows 32-bit and 64-bit

1. Install the latest version of Max 6.1.x from:
<http://cycling74.com/downloads/>
Mira is compatible with both the 32-bit and 64-bit versions of Max 6.1. You will not need to reauthorize the application. The new installer will keep the authorization from your original copy of Max 6.
2. Install Apple “Bonjour” networking libraries from:
<http://support.apple.com/kb/dl999>
Note the Bonjour firewall requirements listed on the page.




3. Download the Mira Package (.zip) from:


http://cycling74.com/direct-download/mira/package_latest_win

The package contains the Mira externals that you will use in your Max patchers.


4. Completely extract the contents of the downloaded .zip file.



5. Once extracted, run the installer application called “C74PackageInstaller”.



6. This installer is not signed. You may see a Windows security dialog appear when you try and run the installer application. You may safely continue the installation.



7. Now that Mira is installed, you may start patching with the Mira objects and your iPad.

If you have any problems with the installation, please contact Cycling '74 technical support.

support@cyclimg74.com